

40 Shades of Grey by Wending Williams Month 6 (Spinning Geese Block)

- 1. Fabrics are right side face up on opposite side from printed side. Laser ink can sometimes run onto the fabric so you always want to be sewing on the printed side and keep the good side of the fabric on the opposite side.
- 2. I use a fabric pencil to mark the sections so that I make sure I am picking up the correct fabric.
- 3. If you cannot see through the paper, fold the sew lines. This helps to judge that the fabric will cover the entire space. I always mark ¼" of where I start. Also trimming along the outer edge (include seam allowance), will help judge full coverage.
- 4. Make your stitch length is smaller so it is easier to remove the paper later. I usually click the down button twice. I would do the smallest where you could rip out the seam if you had to.
- 5. When trimming blocks, make sure you keep the seam allowance along the outside of the block.
- 6. For best results, I suggest go slowly and making sure you are right on the lines,

In case of error: Before ripping out the seam, place a piece of tape over the area that you will be ripping out on the printed side of the paper. This will keep the paper intact so that it won't start ripping until you are ready to remove the paper. I use Scotch tape. Thicker tape will make it hard to remove the paper later.







- 2. Align Piece a right side up and Piece b wrong side up along the crease.
- 3. Sew on line 1. Press.
- 4. Line up card on line between a and c. Fold over paper piece c. Trim.
- 5. Add Piece c. Sew on line 2. Press.

Note: I used an Add-A-Quarter but you can use a ruler to measure ¼".









When adding pieces, make sure it will cover the entire area when flipped. Some will be centered but not all of them. All references to "card" refer to thick paper that helps "catch" the Add-A-Quarter edge.

Numbers on pictures refer to step

6. Line up card on line between c/a/b and d. Fold over paper

7. Add Piece d. Sew on line 3.


outer point fabric (c).


8. Repeat steps adding the flying geese(a), grey inner(b), and

piece d. Trim.

Press.












































When adding pieces, make sure it will cover the entire area when flipped. Some will be centered but not all of them. All references to "card" refer to thick paper that helps "catch" the Add-A-Quarter edge.














- 9. Trim around entire block. Don't cut off seam allowance.
- 10. Sew the four pieces to form a ring.














- 11. Trace the middle circle onto the fabric. My outer circle is $\frac{1}{4}$ " larger than the pattern.
- 12. Fold the middle circle twice so you have a crease. Match of the seams in the flying geese ring and pin.
- 13. Sew along the edge. I use my finger to get out any pucker as I go. SLOW SLOWLY AND REMOVE PINS! I pin a lot but make sure you do not run over any of the pins. When sewing it, I had the middle circle on top and the flying geese on the bottom.

The paper piece is going to have lots of bias edges. BE CAREFUL TO NOT STRETCH!



- 14. Fold the 15 ½" square as shown.
- 15. Trace the pattern into the bottom left corner paying attention to the folds.
- 16. Match of the seams in the flying geese ring with the folds in the piece from step #15 and pin.
- 17. Sew along the edge. I use my finger to get out any pucker as I go. SLOW SLOWLY AND REMOVE PINS! I pin a lot but make sure you do not run over any of the pins. When sewing it, I had the flying geese on top and the outer point fabric on the bottom.
- 18. Make sure the block is 14 $\frac{1}{2}$ ". Trim if necessary.

The paper piece is going to have lots of bias edges. BE CAREFUL TO NOT STRETCH!





15



19



20



19. Add the border to each side.

20. Add the top and bottom to each side.

21. Trim to 15 ½".